



VELOCITY
SOFTWARE

VSIMAIN – Functions and Features

Tim Kessler

MAIN

Velocity Software Inc.

Product Installation and Configuration

The following product packages are available for installation
 Place "X" to mark the directory entries to create or update and press PF4
 Place the cursor on a product package and press PF2 to install

Product Name	Status	Installed Version	Available Packages
INSTALL	Complete	4.3.2.2	4211 4212 4220 4300 4310 4311 4320 4321 4322
PORTAL	Complete	4.4.0.0	4152 4154 4155 4200 4202 4203 4206 4400
SPLUNKFD	Incomplete	<none>	1100
VSESNMP	Incomplete	<none>	4100 4200
ZALERT	Complete	4.3.0.0	4140 4141 4150 4151 4200 4201 4202 4300 4400
ZMAP	Complete	4.3.3.0	4320 4322 4330
ZMON	Complete	4.3.3.0	4232 4233 4300 4301 4302 4303 4304 4305 4330
ZOPER	Complete	4.2.1.1	4120 4123 4124 4200 4210 4211
ZPRO	Incomplete	<none>	3100
ZSSL	Complete	4.2.1.6	4164 4170 4173 4175 4200 4201 4210 4213 4216
ZTCP	Complete	4.3.2.0	4310 4316 4320
ZTUNE	Incomplete	<none>	4110
ZVIEW	Complete	4.3.0.4	4201 4231 4241 4251 4300 4301 4302 4303 4304
ZVWS	Complete	4.3.1.0	4210 4212 4213 4214 4215 4216 4218 4300 4310
ZWRITE	Complete	4.3.3.1	4320 4322 4330 4331

License Key, otype to update:

License Key expires: Aug 2, 2018

PF1: Help PF2: Select PF3: Exit PF4: Disk Config PF5: Key Update PF6: Delete
 PF9: Check for Updates PF10: Config PF11: Install All

Main Screen

- Installation
- Configuration
- Key Update
- Check for Updates

Status

- Must be 'Complete' to install
- 'Incomplete' means Disk Configuration needed
- Errors in red
 - Cursor to error and press F1 for more details

Version

- Installed version
- Red indicates it is not the running version
- Cursor to red version and press F1 for details

Product Packages

- Zero level entire product, others cumulative updates
- Colors
 - White – Available to install, Green – Installed, Blue - Superseded
- Cursor to highest level package and F2 twice to install
- To back out select previous version to install
- F6 to erase product package
 - F6 not on package to uninstall product
- F11 to install all new product packages
 - Will ask for confirmation
 - Walk you through the process
 - Ask to restart all needed servers
- Screen is pageable with F7 and F8

New Installation

- Download Installer & samples for VMSYSVPS & ZVPS
 - Select sample file that fits your environment
- Create VMSYSVPS filepool and ZVPS user
- Install Installer
 - Use automatic installation or download product packages
- F14 to run Disk Configuration on core products
- Create directory entries and ESM definitions
- F11 to Install All

SSI Installation

- Same as new installation except:
 - Disk configuration for all SSI members
 - Disk configuration on base member if adding member
- 192 disk to share files across cluster
- Get first member up and customized before doing next member
- Use automatic install on second & following members

VSIMAINT – Installation

Disk Configuration

- F4 on product line or X in Status area for multiple products
- Define product disk files
 - AUTOV and AUTOG for DIRMAINT and VMSECURE subpools
- Volume and extent information only required new installs
 - Additional web servers can be added
- Creates z/VM directory entries
 - *server* DIRECT and DIRECT *product* files
 - DMALL, VMSALL, DM*product*, VMS*product* EXECs
 - SUBCONFIGs in *server-n* DIRECT files
- Run SFS authorizations
- Create RACF definition files
 - ZVPS RACFALL and *product* RACF files

Product Configuration

- Use Configuration manager rather than XEDIT
 - Field level help and validation
 - Options with default values may not be shown in XEDIT
 - Yellow lines can repeat – F5 to add, F6 to delete
- Multiple ways to configure
 - Menus – F2 on product release, F2 on Edit Run-Time Configuration Files
 - F10 on product line
 - Fast path – VSIMAINT CONFIG *product {memname {memtype}}*
 - PORTAL – zTCP and zWRITE user classes

Product Key Update

- Main screen – F5
- Check for Updates – VSIMAINT, F9, F9
- May not update until top of hour
- Key update status improvements
- Other members in SSI cluster updated

Check for Updates Facility

- Supports HTTP, FTP or FTPS – working on HTTPS
- Active or Passive for FTP
- Proxy servers
- FTP firewall
- Can be used for downloads and uploads
- Automatic invocation option
- D to delete members in user area
- White – Something should consider downloading
- Blue – Don't have, but superseded
- Green – Uninstalled product
- Yellow – In your user area

VSIMAINT – Check for Updates

GETUPDAT

Velocity Software Inc.
Download Installation Packages

Select following new or updated file(s) to download and press PF2

_ HISTORY	README	16-12-19	10:39		Uninstalled products
_ NEWCONFIG	EXECFIX	18-04-27	12:46	_ TUNEFRC	PROD4200 15-09-01 07:19
_ PORTAL	README	17-02-10	14:41	_ VSESNMP	README 17-12-01 15:34
_ ZALERT	README	17-12-11	12:17	_ VSESNMP	PROD4300 17-12-01 15:37
_ ZSSL	README	18-02-06	12:02	_ ZDOC	PROD4220 16-02-05 12:29
_ ZSSL	PROD4219	18-02-06	12:15	_ ZPRO	README 18-06-11 12:03
_ ZTUNE	PROD4100	11-05-25	17:15	_ ZPRO	PROD3101 18-06-12 04:00
_ ZVWS	README	18-06-01	13:45	_ ZPRO	PROD3100 18-05-29 07:59

PF1: Help PF2: Download PF3: Exit
PF6: All Files

PF5: Upload
PF9: Update Key PF12: Cancel

VSIMAINT – Check for Updates

GETUPDAT

Velocity Software Inc.
Upload Files

Specify file(s) to upload and press PF2

<u>*</u>	<u>*</u>	<u>A</u>						
— ABC	DIRECT	14-01-09	09:14	— DEF	DIRECT	14-01-09	09:14	
— ABC-1	DIRECT	14-01-09	08:40	— DEFAULT	WEBHOST	18-02-13	14:56	
— BACKUP	VMFPLCD	17-07-20	15:55	— DIRECT	STCP	14-01-13	14:02	
— BLOCKS	EXEC	14-01-07	18:33	— DIRECT	TTCP	14-01-13	14:03	
— CALC	EXEC	10-11-23	16:22	— DIRECT	ZALERT	16-03-24	17:24	
— CAPFIX	EXEC	14-09-15	09:24	— DIRECT	ZMAP	18-02-27	16:14	
— CHAIN	EXEC	12-12-24	07:22	— DIRECT	ZMON	16-03-24	17:24	
— CHAIN	REXX	12-12-24	07:30	— DIRECT	ZSSL	16-04-25	17:50	
— CLOSECNS	EXEC	14-12-03	05:37	— DIRECT	ZTCP	17-06-01	09:35	
— CLOSECON	EXEC	13-02-16	15:22	— DIRECT	ZTUNE	14-12-03	13:47	
— CMPR	EXEC	12-06-19	10:00	— DIRECT	ZVWS	18-02-27	13:07	
— CMPRX	XEDIT	12-06-19	10:00	— DIRECT	ZWRITE	16-03-24	17:24	
— COMPARE	LISTING	16-11-06	15:35	— DISKCONF	DUMP	15-02-23	14:20	
— CONSOLE	EXEC	11-08-11	17:17	— DISKCONF	EXECNEW	13-12-19	13:44	
— CONSOLE	LIST	18-04-03	15:06	— DISKCONF	EXECOLD	13-12-19	13:40	
— CONSOLE	XEDIT	10-10-06	11:43	— DISKCONF	EXECSSI	15-03-17	11:24	
— CONSOLE	20161229	16-12-29	16:42	— DISKCONF	QSSI	14-06-15	12:13	
— CONSOLE	20161231	16-12-31	23:01	— DMALL	EXEC	18-04-25	10:03	
— CONSOLE	20170101	17-01-01	23:01	— DMSTCP	EXEC	14-01-13	14:02	
— CONSOLE	20170102	17-01-02	23:01	— DMTTCP	EXEC	14-01-13	14:03	
— CONSOLE	20170103	17-01-03	23:01	— DMZALERT	EXEC	16-03-24	17:24	
— CONSOLE	20170104	17-01-04	21:01	— DMZMAP	EXEC	18-02-27	16:14	

PF1: Help PF2: Upload PF3: Exit PF4: Install Packages
PF6: All Files PF8: Down PF9: Update Key PF12: Cancel

VSISSETUP

Velocity Software Inc.
Installation and Configuration

ZWRITE PROD4331

To Install a Product the following must be performed in the order shown
Some functions may not be valid for the selected Product

For additional help press PF1, Press PF3 to return to the previous screen

Function	Valid Function
-----	-----
Run Pre-Installation Tasks	Y
_Product Installation	Y
Run Post-Installation Tasks	N
Edit Run-Time Configuration Files	Y
Restart Server(s)	Y
Stop Server(s)	N
DCSS Configuration	Y
Close Server(s) Console Log	Y

Fast path commands

- VSIMAINT CLOSECON *product*
- VSIMAINT CONFIG *product {filename {filetype}}*
- VSIMAINT RESTART *product*
- VSIMAINT STOP *product*
- VSIMAINT UPLOAD filename filetype filemode (4.4)
- GETUPDAT UPLOAD *filename filetype filemode*

Other Utilities

- Console aggregation – GETCONS
 - Can invoke when ZVPS is logged on
 - Add ZVPS on ESAMAP parameter in ESAPARM EXEC
 - Can consolidate non zVPS users also

PROFILE EXEC

- Don't update PROFILE EXEC, use USERPROF EXEC
- Called at begin and end of PROFILE EXEC
- See USERPROF SAMPLE
- Other products have similar feature with activation call also

VSIMAINT – Installer configuration

INSTALLR

Velocity Software Inc.
INSTALL CONFIG Configuration

INSTALL PROD4322

Auto check for updates NO
Check for updates protocol HTTP
FTP transfer type ACTIVE

Velocity User ID timk
Velocity Password Verify

Proxy server IP or name _____
Proxy port _____

Proxy user ID _____
Proxy password Verify

FTP firewall IP or name _____

Console file aggregation

Receive console logs YES
Max console age 30
Console user ID _____ Override console age _____

PF1: Help PF2: Validate/Save PF3: Exit PF5: Add line PF6: Delete line
PF10: Default PF12: Cancel



timk@velocitysoftware.com